

Novapoint Viewer

Version 20.00.FP6

[User Guide](#)

Version 19.30

The Novapoint Viewer is basically the same application as Novapoint Base, but with the following distinct differences:

- The model is “Read Only” - i.e. it is not possible to create or edit information.

Known issues

- The message “The program can't start because MSVCP120.dll is missing from Your computer” may pop up when Novapoint Viewer is started. To solve this issue, download and install vcredist_x64.exe from: <http://www.microsoft.com/en-us/download/details.aspx?id=40784>.

Language support

If you wish to change the language of the application, it can be changed by doing the following steps:

- Locate your installation folder - e.g. “C:\Program Files\Vianova\Novapoint\Viewer\19.30”
- Locate the file “Novapoint.ConfigSwitcher.exe”
- Change the <configuration> and <language> to your desired settings
- Start the Novapoint Viewer

You can also change the language by adding a parameter to a short-cut file:

- Find the short-cut file, activate right-click menu, select “Properties”
- Target will display “C:\Program Files\Vianova\Novapoint Viewer\NovapointViewer.exe”
- Add -language:eng to the end of the string
- “C:\Program Files\Vianova\Novapoint Viewer\NovapointViewer.exe” -language:eng
- Press “Apply”

The following languages are supported:

- -language:eng = english
- -language:nor = norwegian
- -language:swe = swedish
- -language:dan = danish
- -language:fin = finnish
- -language:fra = french (partly)

Version 19.20

The Novapoint Viewer is basically the same application as Novapoint Base, but with the following distinct differences:

- The model is “Read Only” - i.e. it is not possible to create or edit information.

Known Issues

- Topics is not loaded by default due to a screen scaling problem. The issue does not affect all computers. To test Novapoint Viewer with Topics - start the application with the included shortcut “Novapoint Viewer - Topics”.

Language support

There is currently no interface for changing the language of the application, but it can be changed by doing the following steps:

- Find the desktop icon, activate right-click menu, select “Properties”
- Target will display “C:\Program Files\Vianova\Novapoint Viewer\NovapointViewer.exe”
- Add -language:nor to the end of the string
- “C:\Program Files\Vianova\Novapoint Viewer\NovapointViewer.exe” -language:nor
- Press “Apply”

The following languages are supported:

- no setting = english (default)
- -language:nor = norwegian
- -language:swe = swedish
- -language:dan = danish
- -language:fin = finnish
- -language:fra = french (partly)